



CONTROL PANEL

WWW.MECASIMHARDWARE.COM

INTRODUCTION

This new MECA Control Panel was developed to allow our EVO1 series to be calibrated with advanced settings. This manual covers basic procedures to successfully calibrate your EVO1 series pedals and handbrake.

For any further information, please visit the "Support" section on our website.


CONTROL PANEL SOFTWARE

ORIENTATION IN CONTROL PANEL

Switch between LC and HD brake



Move around screen

Pedal selector



CALIBRATING THE DEVICE


To calibrate your device, click on the "Calibrate" button and follow instructions on the screen



After you have successfully went through calibration procedure, you can adjust the calibrated values using the draggable chart

ADJUSTING CALIBRATION DATA

You can adjust calibration data in two ways - using the number inputs and/or directly dragging one of the 9 points on the chart. Every change you make will automatically show up on the chart.



After you are happy with your settings, you have to click "Save" to save the changes to the device memory.



CONTACT

Email: support@mecasimhardware.com
Website: www.mecasimhardware.com

WWW.MECASIMHARDWARE.COM